



SECURE  
BANCARD

## VALOR DUAL PRICING SETTINGS



# MERCHANT MANAGEMENT



SECURE BANCARD TEST ISO

[Try Beta](#)



1  
Contact

2  
Store

3  
Device

4  
Modules

**ACTIVE** IN-ACTIVE ?  
Last Txn Date: 10-25-2023

Store \*  
SBC Test Store

Device Type \*  
Desktop POS

Debit Share \*  
default

Tag 2

Tag 5

Device Name  
Device1 ( 2121529446 )

EPI \*  
2121529446

Processor \*  
TSYS SIERRA

Serial No

Tag 3

☒ Set as Default

Device \*  
VL100

Label Name \*  
Device1

Tag 1

Tag 4

CASH DISCOUNT/SURCHARGE		TRADITIONAL		GIFT CARD	
MID *	886000000072	V#number *	75009549	Store no *	1076
Bin Number *	686868	Industry *	Retail	Agent Bank Number *	000000
Agent *	0001	<input type="checkbox"/> EBT Cash <input type="checkbox"/> EBT Food	FNS NO	<input type="radio"/> Flat fee amount \$ <input checked="" type="radio"/> Custom fee %	4.000
				Custom fee % *	
				<input type="radio"/> Surcharge <input checked="" type="radio"/> Cash Discount	

Select cash discount,  
custom fee % and enter  
customer-facing rate

# DEVICE MANAGEMENT

## ▶ HOME SCREEN/BIN




APPLICATIONS OPTIONS  
DUAL PRICING

AMOUNT CONFIRMATION BEFORE CARD PROMPT	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO	PRESENT DEVICE TO CUSTOMER	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO
REMOVE SUB TOTAL	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO	ENTERED AMOUNT	<input type="radio"/> CARD PRICE <input checked="" type="radio"/> CASH PRICE
VALIDATE FEE	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO	PROMPT PASSWORD FOR CASH SALES	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
SHOW PRICING ON RECEIPT		<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO	

Blue arrow pointing to the 'CASH PRICE' radio button.

# DEVICE MANAGEMENT



## TIP, TAX & FEE

CUSTOM FEE	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO
ENABLE FOR ALL DEBIT CARDS	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
SIGNATURE DEBIT ONLY	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
CUSTOM FEE DISCLOSURE	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
INCLUDE TIP ON SCREEN	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO
APPLY FEE WITH TIP	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
INCLUDE TAX	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
INCLUDE CASH	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO
CASH DISCOUNT	<input checked="" type="checkbox"/> YES <input type="checkbox"/> NO
CASH DISCOUNT LABEL	
CASH DISCOUNT	
SHOW \$0 DISCOUNT FOR CARD	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
SHOW REMOVE FEE	<input type="checkbox"/> YES <input checked="" type="checkbox"/> NO
LABEL	SURCHARGE %
Adjustment	4.000 %



Must be set to  
no for both types  
of debit